

# Commonly-Used Keystrokes for Curve Fitting/Data Analysis

This section outlines keystrokes that you will need to be familiar with to work the activities in this book.

### **Entering Data**

Data is entered and displayed from the stat list editor. To enter the data:

- 1. Press STAT 1 to select 1:Edit.
- 2. If there are any data presently in the lists, you should first clear the lists. To do this, move the cursor up so that it highlights the heading on the list (L1) you would like to clear. Press CLEAR ENTER to clear the list. Repeat these steps on any list you want to clear.

<b>T</b>	L2	L3	1
HAMPENUR.	13.16 13.64 14.44 15.56 17 10.84	*3.35 *3.1 *2.85 *2.6 *2.35 *2.1 *1.85	_
$L_1 = \{.1, .2, .3, .4\}$			


3. After the lists have been cleared, move the cursor to the list in which you want to place the data, and enter the numbers one at a time. Be sure to press ENTER after each number. After you have finished entering numbers in one column, move to the next column and start data entry again.

### **Displaying the Data as a Plot**

This assumes that you already have the data entered.

- 1. Press 2nd [STAT PLOT] to display the STAT PLOTS Menu.
- 2. To simultaneously turn off all plots that are on, select 4:PlotsOff and press ENTER].
- **3.** To turn on a plot, select the plot and press ENTER, or press the number next to the plot you want to turn on.
- 4. Use the cursor to highlight the type of plot needed and press **ENTER**.
- 5. Complete the Xlist, Ylist, and Mark information for your data set. Press GRAPH to plot the data using your current **WINDOW** settings, or press **ZOOM** 9 to select **9:ZoomStat** to automatically adjust the **WINDOW** settings to fit the data set.






# Fitting an Equation to the Data

**Note:** Students should not be encouraged to use the built-in regression methods until they can fit the same type of curve with other methods, and they understand (or at least have discussed) how the graphing handheld does each fit.


1. Press STAT ▶ to display the STAT > CALC Menu. This menu shows the types of curves the graphing handheld can fit to data sets.




2. Press the number associated with the type of curve you want to fit to the data.

For example, if you want to fit a median-fit line to the data, you would select **Med-Med**. This will return you to the Home screen with the type of curve showing and the cursor blinking, waiting for more input.

- **3.** You need to tell the graphing handheld which two lists you would like to fit to an equation and where you want to store the equation. If you want to let x = L1, y = L2, and the equation to be placed in Y1, you would press: 2nd [L1] , 2nd [L2] , VARS ▶ Function > Y1.
- Med-Med Li,Lz,Yi
- **4.** When you press ENTER, the screen will show the equation and the coefficient values for the function that best fits the data.



5. Press 200M 9 to select 9:ZoomFit, and data will be displayed with the curve superimposed on the plot.




# **Using the Built-in Select Feature**

These data are fairly representative of what might be recorded by a person walking away from a CBR™. The data show two parts. One part is when the person was standing still before starting. The second part is when the person actually started to walk. Assume that you want to work with only the second part of the data.


The depicted data is in L1, L2. We will select out the second part of the data and place it in L3, L4.

1. Press 2nd [LIST]. Press > to go to the OPS Menu. Select 8:Select( and press ENTER).




Select(


**2.** Enter where you want to store the selected data.




**3.** To actually select the part of the graph you will use, press ◀ or ▶ to move to the left end of the data you want to keep, and then press **ENTER**. This sets the left bound.

Press > to move to the right end of the data you want, and press ENTER. This selects the data you want, places them in L3, L4, and displays the graph of L3, L4.







# **Keystrokes for Linking Two Graphing Handhelds**

Connect the two graphing handhelds with the link cable. Push both ends of the cable in firmly.

1. On the RECEIVING graphing handheld, press 2nd [LINK] ▶ to display the **RECEIVE Menu**. Press 1 or ENTER. The message Waiting is displayed.




2. On the SENDING graphing handheld, press 2nd [LINK] to display the SEND Menu. Press the number in front of the type of object you want to send. For this example, assume that you want to send L1 and L2. To do this, select 4:List.



		TRANSMIT
<b>-</b>	L f	LIST
	L 2	LIST
	L3	LIST
	L 4	LIST
	L5	LIST
	Le	LIST
	DIST	LIST

3. Press ▼ to move down the list, pressing


ENTER when you are in front of each item
you want to send. In this example, you would
press ENTER in front of L1 and L2. The
selected items will have a shaded box in front
of them when they have been selected.




**4.** After you have marked the items you want to transfer, press to move to the right and display the **TRANSMIT Menu**. Press ENTER. This will start the transmission.



5. Watch the screen of the receiving graphing handheld. If there is already an object with the same name, you will get a message saying that you are trying to link a **DuplicateName**. Press **2:Overwrite** to overwrite the object and thus get the new object. This will erase the old object with that name. If you need to keep the old object, press **4:Quit**, and then rename the old object and start the process again.



6. After the data has been transferred, you will see a **Done** message.



# **Turning Data into a Program**

**Note:** These instructions assume that the data you intend to save are in **L1**, **L2**.

**1.** Press PRGM ▶ ENTER. The blinking cursor indicates that the handheld is in **ALPHA** mode. If the name includes numbers, press ALPHA to return to numeral mode.



2. Type the name you want, and then press ENTER].





**3.** Press 2nd [RCL] 2nd [L1] ENTER 2nd [RCL] 2nd [L1] ENTER.


This recalls the data in **L1** and puts it in your program.

Press 2nd [RCL] 2nd [L2] ENTER 2nd [RCL] 2nd [L2] ENTER.

This recalls the data in L2 and puts it in your program.







4. Press 2nd [QUIT] to exit.

This ends the simplest version of the program. The data has been placed in the program. When the program is executed, the data will be placed back in L1.

# **Grouping and Archives**

#### Saving Objects as Groups

You have just finished a class in which you collected data for a free-falling object. The data are in L1 and L2. You finally fit a model to the data (Y1), and the bell is about to ring. You need to clear this information out of the graphing handheld and prepare for your next class.

Your options are to run to a computer and save everything or to save it in archive memory as a group on a graphing handheld.

1. Press 2nd [MEM] 8 to select 8:Group.




2. Select 1:Create New, and enter the name you want for the total data you are about to save. In this example, the group is named **P3ACT12** for period 3 activity 12. Press ENTER.




```
GROUP
Name=P3ACT12
```

**3.** Select what you want to save with this name. Because three different types of objects (list, equation, program) are stored in this example, select 2:AII-.







**4.** Move down the list, pressing ENTER beside any object you want stored. When they are selected, the arrow will turn into a square.



**5.** When you have finished your selection, press and ENTER.

The group **P3ACT12** has now been saved in archived memory.






### Ungrouping

1. Press 2nd [MEM] 8 to select 8:Group.






2. Press > to select UNGROUP.


**Note:** The \* next to the names shows that they are in archived memory, not in the regular RAM.


**3.** Press **→** to move down and select the group you want. Press **ENTER** when you are beside an object you want to unarchive.

If the object you are bringing back already exists in RAM, select 2:Overwrite ENTER.

**Note:** Before you ungroup, be sure to group anything that is in your memory that you want to save.







```
Ungrouping:
P3ACT12
L1
• L2
                    LIST
                      Done
```

#### **To Archive or Unarchive**

1. Press 2nd [MEM] 2 to select 2:Mem Mgmt/Del.



**2.** Press  $\overline{\phantom{a}}$  to move down to select the type of object you are going to either archive or unarchive.

To look at programs, for example, press 7:Prgm.

You now see a list of all the programs. Those marked with a \* are already in the archive and thus do not take up the working RAM. Those with no \* are in the working RAM. To change from archived to unarchived, cursor down to the object you want to change, and press ENTER.

After an object has been unarchived, it can be used. Until it is unarchived, it cannot be used.

**Note:** Ungrouping unarchives the objects in the group. Grouping makes an archived copy of the objects.





