

## Get the latest TI-Nspire™ Navigator™ System updates!

To update your TI-Nspire™ or TI-Nspire™ CX Navigator™ System, follow the steps below.

The latest version of TI-Nspire™ technology features improved connectivity between handheld and the access point, therefore it is important that you follow the steps carefully. System requirements have changed, so please review at [education.ti.com/nav/systemrequirements](http://education.ti.com/nav/systemrequirements) before updating. If you have questions or issues, please contact **TI-CARES** at **1.800.842.2737**.

### 1. Update your TI-Nspire™ handhelds

Update your TI-Nspire™ handhelds operating system (OS). You can obtain the latest OS at [education.ti.com/nav/osupdate](http://education.ti.com/nav/osupdate). To successfully install the new OS there must be at least 15MB of free space on the TI-Nspire™ handheld.

Download and save the OS file to a location that you can find easily. *(Note: Once you have upgraded to version 3.9 you are unable to load previous versions of the TI-Nspire OS.)*

- » Go to the **Content workspace** in your TI-Nspire™ Navigator™ Teacher Software. You should see all the connected handhelds. Make sure all handhelds are turned on.
- » From the **Tools Menu**, select **Transfer Tool**. Click on **Add to Transfer List**.
- » Navigate to the folder where the OS file is located.
- » Select the file name and press the **Select** button. The OS file name will appear in the Transfer Tool queue.
- » Click **Start Transfer**.
- » Click **Stop Transfer** when all handhelds have received the OS file.

### 2. Back up your student portfolio database

Before you update you TI-Nspire™ Navigator™ software, you should create a copy of your database as a precaution.

- » Close any open TI-Nspire™ Navigator™ software.

- » Go to the database location.
  - **Windows 7:** C:\Users\[username]\AppData\Local\Texas Instruments\[Name of software]
  - **Windows XP:** C:\Documents and Settings\[username]\Local Settings\Application Data\Texas Instruments\[Name of software]
  - **Mac OS X:** /Users/[username]/Library/Application Support/Texas Instruments/[Name of software]
- » Rename the navNspireTSDB folder to another name (such as *navNspireTSDB-copy*). You may want to sav

### 3. Update your TI-Nspire™ Navigator™ software

- » Download and save the software to a location that you find easily.
  - For Windows: <http://education.ti.com/nspire/update/navtswin>
  - For Mac: <http://education.ti.com/nspire/update/navtsmac>
- » Download and save the software to a location that you find easily.
- » Install the software by double-clicking the icon on your computer.
- » Once installation is complete open the TI-Nspire™ Navigator™ software and follow prompts to associate your TI-Nspire™ handhelds. (Note: Your TI-Nspire™ handhelds must have version 3.9 installed to work with the TI-Nspire™ Navigator™ System.)
- » The TI-Nspire™ CX Wireless Network Adapters or TI-Nspire™ Navigator™ Cradles you have previously set up will be listed as wireless clients in the Network Manager window.
  - If you do not see any adapters and/or cradles listed, launch the set-up wizard and follow the prompts.